



REQUIREMENTS:

- ✓ PMDG 737 NGX
- ✓ FS2Crew PMDG 737 NGX 'REBOOT' Edition. Available at: www.fs2crew.com
- ✓ This tutorial uses **VOICE CONTROL** with **SOP SET 1**

INTRODUCTION:

SOP Set 1 follows stock Boeing procedures to a large degree. Many airlines around the world use stock Boeing procedures, or slightly modified versions of them.

For a full list of voice commands and explanations, please consult the **MAIN OPS MANUAL**.


If you have any questions or problems, please consult the FS2Crew Support Forum at Avsim.com. This is complex software and we're trying to do things as realistically as possible, so don't be afraid to ask questions!

For the Flight Route, we'll leave that up to you. Pick your favorite airport and fly there!

DISCLAIMER: This tutorial is made for flight simulation purposes only and does not necessary reflect real world procedures to their fullest. FS2Crew 737 NGX Reboot is an entertainment product. It is not meant for real-world flying or training. It is not affiliated or associated with any specific airline or company.


LET'S BEGIN:

- If you haven't already trained your voice and set your speech recognizer to **ENGLISH – US**, please do so now. Please consult the MAIN OPS MANUAL for detailed info.
- Load the PMDG 737 NGX from the Free Flight screen. **The PMDG 737 should never be the default aircraft that loads or you WILL have problems.** Do not use saved situation files!
- At this point, you should be sitting in the 2D cockpit and the engines should be running. If the engines are not running, you are probably using a default panel state file, and we generally don't recommend using those as they can sometimes cause the aircraft to initialize improperly.
- We need to shut off the built in **F/O CALLOUTS** or you will get double call outs via the **PMDG – OPTIONS - SIMULATION** menu as shown below:




- We recommend that the F/O's altimeter and Standby altimeter syncs to the Captain's altimeter as shown below.

**SYNC CAPT AND F/O BAR TO 'YES'.
SYNC CAPT AND STBY BARO TO 'YES'.**




Note: The other options, such as Service-Based failures, can be set at your discretion.

- We recommend using EGPWS auto-callouts for the “**MINIMUMS**” and “**PLUS HUNDRED**” calls during approach. Please ensure your PMDG Options are set accordingly as shown below:



- Open the PMDG’s FMC and select the stock **PMDG LONG** or **SHORT PANEL STATE** file. It’s your choice. You don’t need to do this for every flight. In fact, you can start with the engines running. But for the sake of this tutorial we’re going to start with the engines off. These two panel states are generally the most realistic panel state files to use since airline pilots rarely receive the aircraft cold and dark and most major airports supply ground power and air.

- Now we need to open the MAIN PANEL. There is no click spot! Press the button you assigned to open the FS2Crew MAIN PANEL (namely the one linked to **AUTOFEATHER ARM/OFF.**) If you haven't already assigned a button to this event, do it now, or you won't be able to open the MAIN PANEL.



- The FS2Crew MAIN PANEL should open up. It looks like this:




If the Main Panel does not open, double check your keyboard assignment that you assigned to **AUTOFEATHER (ARM/OFF)**. I personally use the “N” key on the keyboard. If the MAIN PANEL still doesn’t appear, try assigning a different key. Also open the PMDG 737’s panel.cfg file with Notepad. Make sure there are FS2Crew entries on it. If not, you forgot to Enable FS2Crew via the FS2Crew Configurator or you have a write permission issue.


The PMDG 737 NGX’s panel.cfg file is located here:

Your Flightsim Folder\SimObjects\Airplanes\PMDG 737-800NGX\panel\panel.cfg

- Press the **SEC** button on the MAIN PANEL. A new panel should open up that looks like an FMC. This panel is called the SECONDARY PANEL.



- Press the **CFG** button on the FMC to open the CONFIG menu.
- Press LSK 1 (Left Line Select Button) to open the **SETUP** page.
- By default, FS2Crew is running in BUTTON CONTROL mode. We need to change that to **VOICE CONTROL**.
- Press LSK 1 to change the Interface to **VOICE CONTROL**.
- Press LSK 4 to change the **SOPS** to **SET 1**.



- The text "**CONFIRM SOP OVERWRITE**" will appear on the same page.



- Press LSK 14 to confirm the overwrite. The various CALLOUTS CFG options will then be updated to match SET 1's SOPs.
- Press the **AUDIO** button on the SECONDARY PANEL.
- Select your **CREW REGION** by pressing LSK 1. This setting controls the regional accent of the crew.
- If you are using a headset, select the audio device associated with your headset by pressing LSK 4 (HEADSET AUDIO DEVICE).
- Press LSK 7 to play the audio test. From your main speakers, you should hear "*Left speaker test... Right speaker test... Audio test complete*".
- Note the button that says **RESET AUDIO SYSTEM**. Only press that if you seem to lose FS2Crew audio; that can happen if your audio device momentarily disconnects from the system.
- Now we need to run the Pre-Flight events. Running the Pre-Flight events is OPTIONAL, but we'll run it anyway for the sake of the tutorial.
- Press the **PF** button on the SECONDARY PANEL to open the PRE FLIGHT EVENTS page.
- Press LSK 4 to run the Preflight Events (your engines must be shutdown first).
- To close the SECONDARY PANEL, press the SEC button on the FS2Crew Main Panel, or click the right screw in the top right hand corner of the SECONDARY PANEL or press the button you assigned to toggle the SECONDARY PANEL.

SOME SIMPLE RULES AND ADVICE:

- In FS2Crew, you are the Captain and the Pilot Flying (PF). The computer is the FO and the Pilot Monitoring (PM).
- If the Autopilot is ON, the MCP (autopilot panel) falls within your area of responsibility. The FO/PM should generally never touch the MCP if the autopilot is on.
- It's highly recommended that you leave the Green Bar on so you can see what the speech recognition system is detecting.

PRE-FLIGHT EVENTS:

The Pre-Flight events are pretty short and intense. These day quick turn arounds are the norm as airlines try to save money. Don't doddle or you will be behind the curve!

This tutorial only covers the key points. For specific details, please consult the FCOMs provided with the NGX. Furthermore, this tutorial assumes it's the first flight of the day for the crew.

Special Note: To **FAST FORWARD** the **PRE FLIGHT EVENTS TIME**, RIGHT CLICK the DOWN ARROW on the FS2Crew Main Panel.

NOTE: All times listed below are approximate.

+25 Minutes: Pre-Flight Events start. Jetway connects if available. Door 1L and cargo doors open.

+24 Minutes: ONLY if using the **COLD AND DARK** panel state (the aircraft has no electrical power) the FO starts the **ELECTRICAL POWER UP SUPPLEMENTARY PROCEDURE** unless you've selected otherwise in the FS2Crew Options menu. Note that in real life, pilots rarely receive the aircraft cold and dark.

ELECTRICAL POWER UP SUPPLEMENTARY PROCEDURE










-CAPTAIN OR FO. TUTORIAL ASSUMES FO WILL DO IT BASED ON DEFAULT CONFIG OPTION.

- ✚ *BATTERY ON*
- ✚ *GROUND POWER SWITCH ON (IF GROUND POWER AVAILABLE)*
- ✚ *FIRE TESTS (FAULT/INOP, OVHT FIRE, EXTINGUISHER)*
- ✚ *START APU IF GROUND POWER NOT AVAILABLE*
- ✚ *CONFIGURE FUEL PUMPS*
- ✚ *WHEEL WELL FIRE TEST*

+23 Minutes: You as the Captain should perform the **PRELIMINARY PREFLIGHT PROCEDURE**. By convention, the Captain will usually perform this procedure if the FO is doing the walk around. If you want the FO to perform this procedure instead of you, select the associated FS2Crew CFG option.

PRELIMINARY PREFLIGHT PROCEDURE

-CAPTAIN OR FO. TUTORIAL ASSUMES CAPTAIN WILL DO IT BASED ON DEFAULT CONFIG OPTION.

-  *IRSs OFF, WAIT APPROX 30 SECONDS, THEN ON*
-  *FLIGHT RECORDER TEST*
-  *VOICE RECORDER SWITCH NORMAL*
-  *SERVICE INTERPHONE SWITCH OFF*
-  *ENGINE PANEL SET*
-  *MACH OVERSPEED TEST*
-  *STALL WARNING TEST (NOTE: REQUIRES AC TRANSFER BUSES ARE POWERED FOR UP TO 4 MINUTES. YOU MAY WISH TO DELAY RUNNING THE FS2CREW PRE-FLIGHT EVENTS BY 4 MINUTES TO ACCOUNT FOR THIS CONDITION.)*
-  *SET PARKING BRAKE (IF BRAKE WEAR INDICATORS WILL BE CHECKED DURING THE EXTERIOR INSPECTION)*
-  *ATIS COPY (NOT SIMULATED)*











+ 22 Minutes: FO starts walk around if he/she hasn't already left. If it's night, the FO will turn on the wheel well light. Captain performs the CDU pre-flight using the estimated ZFW.

+19 Minutes: FA asks if she can start the boarding. Respond: **"YES PLEASE/ GO FOR IT/ OKAY"**. Actual boarding will commence approximately two minute later.

+18 Minutes: FO returns from walk around and starts his **PREFLIGHT** and **CDU PREFLIGHT PROCEDURE**. Capt starts his **PRE FLIGHT PROCEDURE**.

PREFLIGHT PROCEDURE

-CAPTAIN

-  MASTER LIGHTS TEST AND DIM SWITCH TEST
-  EFIS CONTROL PANEL SET (MINIMUMS REF SELECTOR BARO, MINIMUMS SELECTOR EFFRA, FLIGHT PATH VECTOR SWITCH AS NEEDED, BAROMETRIC REFERENCE SELECTOR IN OR HPA, BAROMETIC SELECTOR SET LOCAL ALTIMETER SETTING, VOR/ADF SWITCHES AS NEEDED, MODE SELECTOR MAP, WEATHER RADAR OFF)
-  MODE CONTROL PANEL SET (COURSES SET , FLIGHT DIRECTORS ON, IAS TO V2, BANK ANGLE SELECTOR AS NEEDED, ALT SELECTOR TO 4900 FEET UNTIL AIRWAYS CLEARANCE RECEIVED)
-  OXYGEN TEST AND SET
-  FLIGHT AND STANDBY INSTRUMENTS CHECK
-  PARKING BRAKE SET
-  SET NAV RADIOS
-  AUDIO CONTROL PANEL SET
-  TRIMS CHECK FREE AND SET TO 0
-  VERIFY FLIGHT PLAN

PREFLIGHT PROCEDURE

-FIRST OFFICER. **TUTORIAL ASSUMES FO WILL DO IT BASED ON DEFAULT CONFIG OPTION.**

NOTE: *The various tests (CVR, WX RADAR, TCAS, GPWS) are not part of the normal Preflight Procedure, and are not usually run in during everyday operations. They are 'Supplementary Procedures'. However, if you want the FO to run the Supplementary Procedures during his Preflight flow, select the "PREFLIGHT SUP PROC to "YES" in the FS2Crew Config Options.*

- + YAW DAMPER ON
- + NAVIGATION AND DISPLAYS PANEL SET
- + FUEL PANEL SET
- + ELECTRICAL PANEL SET
- + FIRE DETECTION TESTS IF NOT COMPLETED DURING ELECTRICAL POWER UP
- + EMERGENCY EXIT LIGHTS ARMED
- + WINDOWS HEAT ON
- + PROBE HEAT OFF (ON IF COLD WX OPS)
- + HYDRAULIC PANEL SET
- + AIR CONDITIONING PANEL SET
- + CABIN PRESSURIZATION PANEL SET
- + IGNITION SWITCH RIGHT
- + LIGHTING PANEL SET
- + OXYGEN TEST AND SET
- + DISENGAGE LIGHTS TEST
- + FLIGHT INSTRUMENTS CHECK
- + AUTOBRAKE RTO
- + CARGO FIRE TEST
- + AUDIO CONTROL PANEL SET
- + WEATHER RADAR CONTROL PANEL SET
- + TRANSPONDER CONTROL PANEL SET

At the end of the pre-flight procedure, and if "FUEL UPLOADED REQUIRED" selected to "YES" on the FS2CREW SETUP page, the ground crew will hand the FO the fuel receipt.

+11 Minutes or later: Run the Pre Flight Checklist. Speak: "**PRE FLIGHT CHECKLIST (PLEASE)**".

Checklist Notes:

B = Responded by both flight crew members.

F = Responded by the FO only.

C = Responded by the Captain only.

Items in **RED TEXT** are to be spoken by you, the Captain.

The FO will respond to many of his own challenges if the item falls within his area of responsibility.

If you ever get stuck on a checklist item due to a speech recognition issue, speak **“SET AND CHECKED”**.

PREFLIGHT CHECKLIST (PLEASE)

OXYGEN (B)	TESTED, 100%
NAV TRANSFER & DISPLAY SWITCHES (F)	NORMAL, AUTO
WINDOW HEAT (F)	ON
PRESSURIZATION MODE SELECTOR (F)	AUTO
FLIGHT INSTRUMENTS (B)	HEADING ____, ALTIMETER __*
PARKING BRAKE (C)	SET
ENGINE START LEVERS (C)	CUTOFF

- Trigger key phrase is **“ALTIMETER XXXX”**. Example: **“ALTIMETER TWO NINE NINE TWO”**. Ensure this phrase is said clearly and distinctly from the previously spoken Heading value. Pause a second after saying ‘Heading XXX’.
- **“HEADING”** refers to the aircraft heading shown on the PFD, not the heading value dialed in the MCP.

+10 Minutes: Obtain your airways clearance if using ATC. (In FS2Crew, this is done by the Captain, but in real-life it’s usually done by the FO). Once you’ve received the clearance, enter your cleared Altitude in the MCP Altitude Window.

+9 Minutes: Run the Departure Brief. There are two options: You can open the FS2Crew SECONDARY PANEL and press DEP to and play the Departure Brief there. Or you can speak: **“ARE YOU READY FOR THE DEPARTURE BRIEF?”** Close the brief by asking: **“ANY QUESTIONS?”**

+7 Minutes: Load sheet arrives. If load sheet arrives in person and not via ACARS (as defined in the Config Options), respond: **“THANK YOU/ OKAY THANKS/ THANKS”**.

+6 Minutes: The FO will ask you if you want to start the APU if the Air Start Cart is not connected and the APU is off. Note that the PMDG LONG PANEL STATE uses the Air Start Cart. Reply **“YES PLEASE / GO FOR IT/ OKAY / NO”**. Note: You have a 10 second window to reply.

+5 Minutes: Update the FMC if required. Once **CDU PREFLIGHT** is complete and the load sheet has been reviewed:

- ✚ *ARM AUTOTHROTTLE*
- ✚ *SET V2 IN MCP*
- ✚ *ARM LNAV/VNAV AS REQUIRED. DO NOT ARM LNAV IF EXPECTING VECTORS OR NOT DEPARTING ON A SID*

+3 Minutes: Cargo doors close.

+1 Minute: Boarding is complete. The FA will notify you that the cabin is ready and if she can close the cockpit door. Respond: **“THANKS / THANKS IT WILL BE A SHORT TAXI / THANKS IT WILL BE A LONG TAXI / CLEARED TO CLOSE SHORT TAXI / CLEARED TO CLOSE LONG TAXI”**.

+1 Minute: If the Air Start Cart is not connected and the APU is running and on the busses, the wheel chocks will be automatically removed. The Air Conditioning Cart will also be removed if it is connected.

+1 Minute: If desired, required permission from the Ground Crew to pressurize the hydraulics. Speak: **“COCKPIT TO GROUND”**.... **“CAN WE PRESSURIZE THE HYDRAULICS?”** NOTE: Making this request will override your FS2Crew CFG Option to have HYD SYSTEM A depressurized. The FO will turn on HYD A PUMPS during his Before Start Flow regardless of your CFG setting. Unless the Air Start Cart is required for engine start, ask the Ground Crew to disconnect the ground equipment. Ensure you have a power source on-line first, such as the APU!

+ 0 Minutes: After being cleared for engine start (not simulated) and after the exterior doors are closed, and, if desired, after ground has cleared you to pressurize the hydraulics, speak: **“BEFORE START PROCEDURE”** and perform the **BEFORE START PROCEDURE**.









BEFORE START PROCEDURE

-CAPTAIN

- ✚ *SELECT TAKEOFF PAGE ON CDU*
- ✚ *FLIGHT DECK WINDOWS LOCKED*
- ✚ *OBTAIN CLEARANCE TO PRESSURIZE THE HYDRAULICS AND START THE ENGINES*
- ✚ *TAKEOFF TRIM / RUDDER & AILERON TRIM SET*

BEFORE START PROCEDURE

-FIRST OFFICER

-  FLIGHT DECK DOOR CLOSED AND LOCKED
-  SELECT LEGS PAGE ON CDU
-  EXTERIOR DOORS VERIFY CLOSED
-  FLIGHT DECK WINDOWS LOCKED
-  FUEL PANEL SET
-  HYDRAULIC PANEL SET (HYD A PUMPS OFF IF PUSHBACK REQUIRED AND ASSOCIATED CFG OPTION SELECTED).
-  ANTI COLLISION LIGHT ON
-  LOWER DU TO ENGINE

+0 Minutes: Speak: “**BEFORE START CHECKLIST**”.

BEFORE START CHECKLIST (PLEASE)

FLIGHT DECK DOOR (F)	CLOSED AND LOCKED
MCP (C)	V2____, HEADING____, ALTITUDE____*
TAKEOFF SPEEDS (C)	V1____, VR____, V2____*
CDU PREFLIGHT (C)	COMPLETED
RUDDER AND AILERON TRIM (C)	FREE AND ZERO
TAXI AND TAKEOFF BRIEFING (C)	COMPLETED
ANTI COLLISION LIGHT (F)	ON

- Trigger key phrase is “ALTITUDE”. Example: “ALTITUDE SEVEN THOUSAND / ALTITUDE FLIGHT LEVEL NINE ZERO”. Ensure this phrase is said clearly and distinctly from the previously spoken heading value.
- Trigger key phrase is “VEE TWO”. Example: “VEE TWO IS ONE FOUR SIX”. Ensure this phrase is said clearly and distinctly from the previously spoken VR value.

+ 0 Minutes: Pushback and Engine Start.

PUSHBACK AND ENGINE START:

- For pushback, use the built in PMDG pushback until Ultimate Ground Crew X is released.
- Speak “**START SEQUENCE IS TWO THEN ONE**”.
- Use one of the following voice commands to start engine two:
 - **START NUMBER TWO ENGINE**
 - **START ENGINE TWO**
 - **START RIGHT ENGINE**
 - **TURN NUMBER TWO**
- At around 25 percent N2, manually move the right fuel control lever to IDLE CUTOFF.
- The FO will call “**STARTER CUTOUT**” when the START VALVE LIGHT extinguishes.

Special Note: If you experience that the FO calls “Starter Cutout” before he should, ensure you have no hardware or other controls assigned to the stock FS “Mixture” control event.

- If it’s a hot day and you delayed the APU start (if using the APU at all), command the FO to isolate a pack after engine two stabilizes. This will help get cool air to the passengers since the engines can cool the plane faster than APU bleed air. Speak: “**ISOLATE A PACK**”.
- Start Engine 1 using the same procedure.
- Note: If doing a cross bleed start, the start sequence would be one then two.

CROSS BLEED ENGINE START

- Cross Bleed starts are generally only used if the APU is inoperative.
- Speak: “**START SEQUENCE IS ONE THEN TWO**”.
- If engine 1 is not running, speak: “**START ENGINE ONE**”.
- After engine 1 has started, advance the throttle on engine 1 until the bleed duct pressure is about 30 PSI.
- Speak: “**START ENGINE TWO CROSS BLEED START**”.

BEFORE TAXI PROCEDURE:

- The FO will automatically start his BEFORE TAXI PROCEDURE after both engine have stabilized. He will complete all actions up to and including the ENGINE START SWITCHES. Then he will wait for you to request the Takeoff Flaps and complete the Flight Controls Check before completing the remaining items in his flow. To ask for the Takeoff Flaps, speak, for example, “**FLAPS FIVE**” or whatever takeoff flap you desire to use.

BEFORE TAXI PROCEDURE

-CAPTAIN

- ✚ *COMMAND THE FO TO SET THE TAKEOFF FLAP AFTER THE FO SETS THE ENGINE START SWITCHES TO CONTINUOUS*
- ✚ *FLIGHT CONTROLS CHECK PERFORM*

BEFORE TAXI PROCEDURE

-FIRST OFFICER

- ✚ *EAI/WAI ON IMMEDIATELY AFTER ENGINE START IF REQUIRED*
- ✚ *ENGINE GENERATORS ON*
- ✚ *PROBE HEAT ON*
- ✚ *PACKS AUTO*
- ✚ *APU OFF*
- ✚ *ENGINE START SWITCHES CONTINUOUS*
- ✚ *BLANK LOWER DISPLAY UNIT*

AFTER “**FLIGHT CONTROLS CHECK COMPLETE**”:

- ✚ *TRANSPONDER AS REQUIRED (After Flight*
- ✚ *RECALL*

- After you’ve called for the Takeoff Flaps, It’s time to run the flight controls check. Speak: “**CONTROL CHECK**” or “**FLIGHT CONTROLS CHECK.**”
- Move the control column fully left and speak “**FULL LEFT... CENTER**”.
- Move the control column fully right and speak “**FULL RIGHT... CENTER**”
- The FO will respond “**CHECKED**”.
- Perform the same check with the elevators: “**FULL UP... FULL DOWN... CENTER.**”
- Then rudders: “**FULL LEFT... CENTER... FULL RIGHT... CENTER**”.
- When done, speak “**FLIGHT CONTROLS CHECK COMPLETE.**” That phrase is the trigger for the FO to complete the remaining two items in his procedure. DO NOT FORGET TO SPEAK THIS PHRASE OR THE FO WILL NOT COMPLETE HIS FLOW.
- Now it’s time to run the Before Taxi Checklist. Speak: “**BEFORE TAXI CHECKLIST (PLEASE)**”.
- If it’s night, the FO will turn off the Dome Light at the end of the checklist.

- The FO will turn on the TAXI LIGHT, and, if it's night, the RUNWAY TURN OFF LIGHTS after the GROUND EQUIPMENT CHALLENGE.

BEFORE TAXI CHECKLIST (PLEASE)

GENERATORS (F)	ON
PROBE HEAT (F)	ON
ANTI-ICE (F)	_____
ISOLATION VALVE (F)	AUTO / CLOSED
ENGINE START SWITCHES (F)	CONT
RECALL (B)	CHECKED
AUTOBRAKE (F)	RTO
ENGINE START LEVERS (C)	IDLE DETENT
FLIGHT CONTROLS (C)	CHECKED
GROUND EQUIPMENT (B)	CLEAR

COLD WEATHER PROCEDURES

- During the Before Taxi procedure, instead of calling for the Takeoff Flaps, speak: "**LEAVE THE FLAPS UP FOR TAXI**".
- When near the runway, call for the desired takeoff flap PRIOR to calling for the BEFORE TAKEOFF CHECKLIST. Example: "**FLAPS 5**".

TAXI:

- Optional: Speak "**CLEAR LEFT / CLEAR ON THE LEFT**" even though it's redundant.
- The FO will blank the lower screen.
- Taxi to runway.

APPROACHING RUNWAY:

- The FA will notify the cockpit that the cabin is secure. The FO will answer the service interphone and notify you that the cabin is secure. Note: You cannot takeoff until the cabin is secure. You may line-up and wait on the runway while waiting for the cabin secure call.
- After the cabin is secure, run the BEFORE TAKEOFF CHECKLIST. Speak: “BEFORE TAKEOFF CHECKLIST (PLEASE)”.

BEFORE TAKE OFF CHECKLIST (PLEASE)

FLAPS (C)

FLAPS X GREEN LIGHT/ X GREEN LIGHT

STABILIZER TRIM (C)

5 POINT 4 UNITS

Note: The Stabilizer trim will only accept a trim setting to one decimal place. So 5.0 Units will work, but not 5.57 units. You are supposed to be looking at the trim handle, not the CDU for the trim setting.

If you need to cross any runways, you may speak: “CONFIRM CLEARED TO CROSS RUNWAY XXX / CONFIRM CLEARED TO ENTER RUNWAY XXX”

RUNWAY ENTRY PROCEDURE AND TAKEOFF:

- Speak: “**RUNWAY ENTRY PROCEDURE / BEFORE TAKEOFF PROCEDURE/ CLEAR TO BACK TRACK**”
- Speak: “**CLEAR LEFT / CLEAR ON THE LEFT**”.

BEFORE TAKEOFF PROCEDURE

-PILOT FLYING

- ✚ WEATHER RADAR, VSD, TERRAIN AS DESIRED
- ✚ TRAFFIC ON ND

BEFORE TAKEOFF PROCEDURE

-PILOT MONITORING

- ✚ PA: “CABIN CREW TAKE YOUR SEATS”
- ✚ STROBES ON
- ✚ FIXED LANDING LIGHTS ON / OTHER LIGHTS AS REQUIRED
- ✚ TRANSPONDER TARA
- ✚ TERRAIN / WEATHER AS BRIEFED

- Speak “**TAKEOFF**” after cleared by ATC for takeoff.
- The PM will then set the RETRACTABLE LANDING LIGHTS to ON.
- Advance the thrust levers to 40%, wait for the engines to stabilize, then press TOGA.
- At this point, the FMAs should be called out. Speak: “**N1 TO GA**”. Pronounce TOGA as “Tow Ga”. The PM will reply “**CHECKED**”. Do not make any more FMA callouts until 400 feet.
- PM will call “**THRUST SET**” and “**80 KNOTS**”.
- When the PM calls 80 Knots, speak “**CHECKED**” to confirm you are not incapacitated and that the ASI’s agree.
- The PM will call “**V1**” if V1 is not selected an aircraft auto-callout.
- When the PM calls “**ROTATE**”, pitch the nose up.
- After the PM calls “**POSITIVE RATE**”, speak: “**GEAR UP**”.
- Note: The PM will not announce “GEAR UP” because it’s Boeing practice not to say anything between V1 and 400 feet except for “ROTATE” and ‘POSITIVE RATE”, even if you have a failure. At 400 feet, you should also start announcing FMA changes again.

REJECTED TAKEOFFS

- If Speak: “**REJECT REJECT**”.
- If you want to return to the runway, speak: “**LETS TAXI BACK TO THE RUNWAY**”.
- If desired, you make the following voice commands should an evacuation be required: “**THIS IS THE CAPTAIN EVACUATE EVACUATE EVACUATE**” or simply “**EVACUATE EVACUATE EVACUATE**”.
- You may also wish to make PAs from the **PA - QRH** screen in the SECONDARY PANEL depending on the context.
- Note: If you want to return to the runway, ensure you don’t stow the speedbrake while the mode displays ‘Okay to Clean Up’ or you may trigger the FO’s After Landing procedure.

VOICE CONTROL REMINDERS!

If you ever get stuck on a checklist item, speak: “**SET AND CHECKED**” to advance to the next item.

If an autopilot value don’t stop when it should, speak “**CANCEL LAST COMMAND**”.

CLIMB:

- If LNAV was not armed on the ground, engage a lateral mode at 400 feet. If the autopilot is on, press LNAV yourself since the MCP is the Pilot Flying’s area of responsibility with the autopilot on. If the autopilot is off, speak: “**ENGAGE LNAV / SELECT LNAV / ENAGE HEADING SELECT / SELECT HEADING SELECT**”.
- If not using VNAV and the autopilot is off, speak: “**SET FLAPS UP SPEED**” passing the acceleration altitude. The PM will then set the Flaps Up Speed in the airspeed window. However, if the autopilot is on, then you control the autopilot panel and you would set the Flaps Up Speed manually.
- Retract the flaps on schedule using the following commands (assuming takeoff was done at Flaps 5): “**FLAPS 1**”, “**FLAPS UP / FLAPS ZERO**”.
- The PM will start his AFTER TAKEOFF PROCEDURE automatically when the flaps are up and the aircraft is above the clean speed.

AFTER TAKEOFF PROCEDURE

-PILOT MONITORING

- ✚ *ENGINE START SWITCHES OFF (UNLESS ANTI ICE IS ON)*
- ✚ *RUNWAY TURN OFF, RETRACTABLE AND TAXI LIGHTS OFF*
- ✚ *AUTOBRAKE OFF*
- ✚ *GEAR OFF*

- Speak **“AFTER TAKEOFF CHECKLIST (PLEASE)”**
- The PM will perform entire checklist on his own.
- The PM will ask you if you want to release the Cabin Crew so they can begin their inflight service. Speak: **“YES/ OKAY/ GO FOR IT/ NO”**.
- In real-life, the Pilot Flying (that’s you!) would usually turn on the autopilot himself, but if you want the PM to turn on the autopilot you may use this voice command: **“SELECT AUTOPILOT ON (PLEASE) / SELECT COMMAND A (PLEASE)”**.
- If VNAV was not armed on the ground, engage VNAV when desired. If the autopilot is on, press VNAV on the MCP panel. If the autopilot is off, speak: **“ENGAGE VNAV/ SELECT VNAV”**.
- At 10,000 feet, the PM will call **“10,000/ FLIGHT LEVEL 100”**, and he will turn off the fixed landing lights unless otherwise selected in the FS2Crew CFG Options. (Some airlines, for example, only turn off the landing lights at the Transition Altitude or even cruise).
- Shortly after passing 10,000 feet above the departure airport elevation, the PM will ask you if you want to release the cabin (the passengers). Speak: **“YES/ OKAY/ GO FOR IT/ NO”**.
- Passing Flight Level 290, check that the two main altimeters are within 200 feet of each other. Speak **“WE ARE OKAY FOR R V S M”**. (You should also do this check at the Top of the Climb and every hour in cruise you are above FL290).

WORKING WITH THE FMC:

If making a change in the FMC, prior to pressing the EXEC button, speak: **“CONFIRM EXECUTE”**. The PM will reply **“CONFIRM”**. You can then press the EXEC button.

CREW COORDINATION TIPS:

With the autopilot on, only you as the PF should touch the autopilot panel. However, if you change an autopilot value, you should inform the PM as part of good Crew Resource Management. If, for example, you manually set Speed 250 in the Speed window, you can speak: **“SPEED 250”**. The PM will respond: **“CHECKED”**.

TRANSITION ALTITUDE:

- Passing the Transition Altitude (as defined in the PMDG FMC), the PM will call “**TRANSITION ALTITUDE, SET STANDARD**”.
- You should then set STD on your side (press the STD button) and set the standby altimeter / IFSD.

CRUISE:

- If you wish to communicate with the FA, press the **CALL ATTD** button on the overhead panel or open the **FA PAGE** in the **SECONDARY PANEL**. If you press the CALL ATTD button, you will hear a chime a few seconds later when the Cabin contacts you. Speak: “**HELLO FLIGHT DECK**” to answer the FA. Use the available responses from the MAIN OPS Manual to reply.
- In cruise, there is not much to do other than monitor the instruments.

DESCENT PROCEDURE

- Approximately 150 miles back of the Top of Descent, Open the **SECONDARY PANEL**.
- Press **APP** to open the **APPROACH BRIEF PAGE**.
- Make your desired selections by pressing the Left Line Select buttons on the Approach Brief Page.
- You need to manually enter altitudes for the Decision Altitude, Missed Approach Altitude and Final Approach Fix.
- Enter the desired value in the scratch pad, then press the left LSK button associated with the field you wish to update.
- Do **NOT** run the Approach Brief yet. The Approach brief comes at the end of the Descent Procedure.
- Speak: “**LETS START SETTING UP FOR THE DESCENT**”.
- That is the trigger for both crew members to start their descent procedure.

DESCENT PROCEDURE

-PILOT FLYING

- ✚ SET MINS SELECTOR (RADIO IF CATII or III OTHERWISE SELECT BARO)
- ✚ SET DECISION ALTITUDE/HEIGHT AND SELECT APP/BCRS ON STANDBY/IFSD.
- ✚ VERIFY OR SET THE TRANSITION LEVEL ON THE FMC'S DESCENT FORECAST PAGE.
FS2CREW NEEDS THAT VALUE TO COMPUTE THE PM'S 'TRANSITION' CALL.
- ✚ PERFORM APPROACH BRIEF



DESCENT PROCEDURE

-PILOT MONITORING

- ✚ RECALL
- ✚ SELECT VREF
- ✚ SET DA/DH ON EFIS PANEL (NOT SIMULATED DUE TO SDK LIMITS)
- ✚ SET AUTOBRAKE
- ✚ IF RNAV APPROACH, SET VOR UPDATING OFF

- After the PM has completed his descent flow, brief for the Approach by pressing the **PLAY BRIEF** button on the Approach Brief page.
- As an option, you can speak: **“ARE YOU READY FOR THE APPROACH BRIEF?”** You must then close the brief by speaking: **“ANY QUESTIONS”**.

DESCENT CHECKLIST

- The Descent checklist should be completed before the airplane descends below 10,000 MSL for arrival. Generally, though, you would run it prior to the Top of Descent.
- Speak: “DESCENT CHECKLIST (PLEASE)”.

DESCENT CHECKLIST (PLEASE)

PRESSURIZATION (PM)	LAND ALT ____
RECALL (PM)	CHECKED
AUTOBRAKE (PM)	____
LANDING DATA (B)	VREF __, MINIMUMS __ FEET*
APPROACH BRIEFING (PF)	COMPLETED

*NOTE: For ‘Landing Data’, XXXX FEET is the trigger. Ensure that is said clearly and distinctly. Speak “SET AND CHECKED” if stuck.

PASSING THE TRANSITION LEVEL:

- Ensure that you entered a TRANSITION LEVEL value on the PMDG 737’s FMC’s DESCENT FORECAST PAGE. That value is used to trigger the PM’s transition level call.
- PM: “TRANSITION LEVEL, ALTIMETERS RESET XXXX”.
- The PM will then press the STD button on his EFIS panel and set the local altimeter. Note that your altimeter as well will be updated to local pressure when the PM updates his altimeter. This is an FS limitation we can do nothing about.
- If you would rather the FO not set your Baro altimeter and just call “TRANSITION”, use the **MOD TL CALL SOP 1** option on the **CONFIG – MISC (2)** page.
- Special note: During descent, even if above the TL, QNH must be set before crossing the IAF, vectors to final or base to final as a part of the Approach Procedure and prior to the Approach Checklist. This can sometimes pose a problem in Asia or Europe where the Transition Levels can be as low as FL35. If you need the Pilot Monitoring to set QNH prior to crossing the TL, speak “SET TRANSITION / SET QNH/ SET ALTIMETERS”.
- For an ILS/LOC approach, select the ILS frequency if it is standby and identify.

APPROACH:

- After passing the Transition Level, Speak: “**APPROACH CHECKLIST (PLEASE)**”.

APPROACH CHECKLIST (PLEASE)

ALTIMETERS (B)

____ SET

*Example response. 2992 SET. 1013 SET. You must say “**SET**” at the end or the FS2Crew Mode will not change to the next mode.*

- Passing 10,000 feet (unless otherwise selected on the FS2Crew CFG Options page), the PM will turn on the fixed landing lights, the logo lights as required and set the seatbelts signs to on.
- If AUTOLAND was selected in the APPROACH BRIEF for the APPROACH TYPE, the PM will turn on the APU for electrical redundancy.
- At approximately 10000 feet above the arrival airport elevation, the PM will make a PA: “**CABIN CREW PREPARE FOR LANDING.**”
- At approximately 5000 feet above the arrival airport, the FA will notify the cockpit that the cabin is secure.

SHOOTING THE APPROACH:

- Use HDG SEL or LNAV to intercept the final approach course. If using LNAV, ensure the localizer is captured as it might parallel the approach course.
- Arm APP Mode if required. If dual channel approach desired, arm second autopilot.
- Speak: “**FLAPS 1**” (Special Tip: If the autopilot off, speak: “**FLAPS 1 MATCH SPEED**”). The PM will set Flaps 1 speed for you. You can use this same syntax for the subsequent flap calls as well.
- Speak: “**FLAPS 5**”.

TRANSITIONING TO A VISUAL APPROACH:

If you can see the runway and you wish to continue visually, speak: “**VISUAL**”. That will change the Approach Type to Visual. Then speak: “**CANCEL THE BAROS/ RESET THE BAROS**”. You should then press the RST button on your MINS selector. The PM will stop making callouts relevant to the instrument approach. Note: On a Visual and sometimes on a VNAV/IAN approach (especially in hot conditions), you should call “**CYCLE FLIGHT DIRECTORS**” or “**RECYCLE THE FLIGHT DIRECTORS**” after the autopilot is disengaged.

- The PM will call “**LOCALIZER ALIVE**” and “**GLIDESLOPE ALIVE**”. Speak “**CHECKED**”. Note: Your heading bug and ILS course bug must be within 90 degrees of each other for this call to be triggered.
- When the Glideslope comes alive, speak: “**GEAR DOWN FLAPS 15**”. Arm the speed brake.
- The PF will warn you if the speedbrakes are still up with Flaps 15 set.
- When the Radar Altimeter comes alive, the PM will make a PA: “**CABIN CREW TAKE YOUR SEATS.**”
- At Glideslope capture, speak: “**FLAPS 30/40**”.
- Assuming the autopilot is on, manually set the Missed Approach Altitude in the MCP at Glideslope Capture. If the autopilot is off, command the PM to set the Missed Approach Altitude. Speak: “**SET MISSED APPROACH ALTITUDE**”.
- If autopilot not engaged, speak: “**SET VREF PLUS ____**”
- If autopilot engaged, manually set VREF plus additive.
- Passing the Outer Marker or FAF/FAP, the PM will call “**OUTER MARKER / FINAL APPROACH FIX, HEIGHT CHECKED, MISSED APPROACH ALTITUDE SET**”. Speak: “**CHECKED**”.
- After the final landing flap has been selected, speak: “**LANDING CHECKLIST**”.

LANDING CHECKLIST (PLEASE)

ENGINE START SWITCHES (PF)	CONTINUOUS
SPEEDBRAKE (PF)	ARMED
LANDING GEAR (PF)	DOWN
FLAPS (PF)	FLAPS 15/30/40 GREEN LIGHT

- When passing the stability gates (1000 feet in IMC and 500 feet in VMC), PM will call “**STABLE**” or “**NOT STABLE**”.
- If autopilot not engaged, speak: “**SET VREF PLUS ____**”
- If autopilot engaged, manually set VREF plus additive.
- Speak: “**CLEARED**” when cleared to land.
- At minimums, the PM will speak: “**APPROACH LIGHTS**”. Reply: “**CONTINUE**” if you can see the lights, otherwise speak: “**GO AROUND FLAPS 15**” if you don’t have the required visual reference.
- The PM will speak: “**THRESHOLD**” or “**RUNWAY**” when he can see the landing environment. Reply: “**LANDING**”.
- Note: The PM’s ability to make the Approach Lights and Threshold/Runway calls are based on visibility data read out of the simulation. Do not expect perfection with these callouts. FS2Crew cannot “see” what you see on your monitor.
- When you speak LANDING, the PM will turn on Retractable Landing Lights, Runway Turnoff Lights and Taxi light.
- If you need to go around, speak: “**GO AROUND FLAPS 15**” and check the GO AROUND SECTION in the manual for more info.

GO AROUND PROCEDURES

- Push the TO/GA switch
- Speak: **“GO AROUND / GO AROUND FLAPS 15”**.
- After the PM announces **“POSITIVE RATE”**, speak: **“GEAR UP”**.
- The PM will set the landing gear up.
- At or above 400', select or call for a lateral roll mode.
- At the acceleration altitude, speak: **“SET FLAPS UP SPEED”** if VNAV is not engaged.
- Retract the flaps on schedule and call for the **“AFTER TAKEOFF CHECKLIST”**.

ROLLOUT

- The PM will announce the status of the speed brakes and reverses. **“SPEED BRAKE UP/ NOT UP/ REVERSES NORMAL”**.
- The PM will call **“60 KNOTS”**. Speak: **“CHECKED”**.
- The PM will call auto brakes disarmed. Speak: **“CHECKED”**.

AFTER LANDING

To trigger the FO's after landing flow, position the speed brake down or speak **“OKAY TO CLEAN UP”**.

AFTER LANDING PROCEDURE

-CAPTAIN

- ✚ *SPEED BRAKE DOWN*
- ✚ *WX RADAR (EFIS PANEL) OFF*

AFTER LANDING PROCEDURE

-FIRST OFFICER

- ✚ *APU (AS SELECTED ON APPROACH BRIEF)*
- ✚ *PROBE HEAT SWITCHES OFF*
- ✚ *LIGHTS*
- ✚ *ENGINE START SWITCHES OFF (UNLESS ANTI ICE REQUIRED)*
- ✚ *WEATHER RADAR (FO'S EFIS PANEL) OFF*
- ✚ *AUTOBRAKE OFF*
- ✚ *FLAPS UP (FLAPS 15 IF CONTAMINATED)*
- ✚ *TRANSPONDER*

Note: If, in the APPROACH BRIEF, you selected **POWER/AIR: APU (DELAYED START)**, the FO will NOT start the APU on his own. You will need to tell him when to start the APU. Speak: **“START THE APU”**.

If, in the APPROACH BRIEF, you selected **POWER/AIR: APU (A.LDG PROC)**, the FO will start the APU on his own during his After Landing flow.

- Speak: **“CLEAR LEFT / CLEAR ON THE LEFT”** if crossing another runway.

TAXI IN

- If you require APU power, and if you did not select the FO to automatically turn on the APU during the AFTER LANDING PROCEDURE in the APPROACH BRIEF, speak **“TURN ON THE APU / START THE APU”** when desired. Turn it on as late as possible to save fuel.
- If desired, shut down engine number two to save fuel. See the Engine Shutdown procedure described after the TAXI section in this tutorial.
- Just prior to turning into the gate or stand, speak: **“LIGHTS AND DOORS”**. The FO will turn off the taxi and runway turnoff lights and make the following PA: **“CABIN CREW DISARM DOORS AND CROSSCHECK.”**
- If the APU is running, he will put the generators on the APU and state: **“DOORS DISARMED, APU ON THE BUS”**. If the APU is not running, he will state: **“DOORS DISARMED, NO APU.”**

SINGLE ENGINE TAXI:

- If you wish to shut down an engine during taxi to save fuel, follow this procedure.
- Wait three minutes for engine cool down prior to shutting down the number two engine. The FO will announce when three minutes are up.
- Note that the area of responsibility for the engine fuel lever depends on if the aircraft is moving or stationary.
- FSX has a ground friction problem that can make single engine taxiing very difficult. You may wish to use this solution.
- - ✓ Install FSUIPC if you do not already have it (www.schiratti.com)
 - ✓ Go to this folder in your FS directory: **/Modules/FSUIPC Documents/Example LUA Plugins.zip**
 - ✓ Copy “DynamicFriction.lua” from that zip file and put it in your **FS/Modules** folder.
 - ✓ Open your **FSUIPC4.ini** file with Notepad.
 - ✓ Add these lines:
 - **[Auto]**
 - **1 = LUA DynamicFriction**

IF AIRCRAFT MOVING:

- Speak: “**SHUTDOWN RIGHT ENGINE / SHUTDOWN NUMBER TWO ENGINE**”
- The FO will place his virtual hand on the engine two start lever.
- The FO will speak: “**ENGINE START LEVER NUMBER TWO CONFIRM**”.
- Speak: “**CONFIRMED**”.
- The FO will then set the FUEL LEVER to CUTOFF for engine two.

IF AIRCRAFT STATIONARY:

- Put your mouse on the number two start lever and speak: “**ENGINE START LEVER NUMBER TWO CONFIRM**”.
- The FO will respond “**CONFIRMED**”.
- Manually set FUEL LEVER #2 to CUTOFF.

GATE/STAND ARRIVAL

- When you park at the gate or stand, set the parking brake and ensure the **taxi light is off**.
- **THE TAXI LIGHT MUST BE OFF** as it is a necessary condition for the FO’s shutdown flow to initiate.
- If the three minute engine cool down time has not been reached, the FO will announce that three minutes have not been reached. If the APU is not on the busses or no Ground Power is available, the FO will announce that no power is available.

GATE/STAND ARRIVAL SHUTDOWN

SHUTDOWN PROCEDURE

-CAPTAIN

-  *PARKING BRAKE SET*
-  *ENGINE START LEVERS CUTOFF (ENSURE POWER SOURCE AVAILABLE FIRST!)*
-  *FLIGHT DIRECTOR OFF*

SHUTDOWN PROCEDURE

-FIRST OFFICER

- ✚ APU OR GPU ON THE BUSES
- ✚ SEATBELTS OFF
- ✚ ANTI COLLISION LIGHT OFF
- ✚ FUEL PUMPS OFF (UNLESS APU RUNNING)
- ✚ ENGINE START SWITCHES OFF
- ✚ ANTI ICE OFF
- ✚ ELEC HYDRAULIC PUMPS OFF
- ✚ PACKS AUTO
- ✚ ISOLATION VALVE OPEN
- ✚ APU BLEED ON (IF USING APU)
- ✚ LIGHTS AS REQUIRED
- ✚ FLIGHT DIRECTOR OFF
- ✚ RESET TIMER

When the shutdown procedure is complete, call for the SHUTDOWN CHECKLIST. Speak: “**SHUTDOWN CHECKLIST**”.

SHUTDOWN CHECKLIST (PLEASE)

FUEL PUMPS (F)	OFF
PROBE HEAT (F)	OFF/AUTO
HYDRAULIC PANEL (F)	SET
FLAPS (C)	UP
PARKING BRAKE (C)	SET /RELEASED
ENGINE START LEVERS (C)	CUTOFF
WEATHER RADAR (B)	OFF

Note: If you want to make a second flight, you do NOT need to reload the aircraft. Instead, press the down arrow button on the FS2Crew Main Panel, skip over the SECURE CHECKLIST. You will be returned to the PRE-FLIGHT CHECKLIST.

Note: If you unlock the cockpit door via the knob on the center console, you can hear the sound of the passengers deplaning.





SECURING THE AIRCRAFT

If you wish to secure the aircraft, use the following procedure:

- Speak: “**SECURE THE AIRCRAFT PLEASE**”.
- When the FO completes his flow, speak: “**SECURE CHECKLIST**”.

SECURE PROCEDURE

-FIRST OFFICER

-  *IRS'S OFF*
-  *EMERGENCY EXIT LIGHTS OFF*
-  *WINDOW HEAT OFF*
-  *PACKS OFF*

SECURE CHECKLIST (PLEASE)

IRSS (F)	OFF
EMERGENCY EXIT LIGHTS (F)	OFF
WINDOW HEAT (F)	OFF
PACKS (F)	OFF

-TUTORIAL END-